Release notes v6.1

XEC Director Release v6.1 – w/c Oct 5th 2020

What's new

- 。 Advanced automatic user profiling
- Support for multiple Workflows and Watchlists
- Disk space warning
- $_{\circ}~$ Secure communication icon
- Mircosoft Endpoint Configuration Manager support

Advanced automatic user profiling


Improved user profiling including automatic settings based on historical data. You can now set a time span and the minimum number of extraction activities for specific users. If the criteria are not reached within the time span, the user will be downgraded. To upgrade users, you should manually assign the user level.

User levels can be used to determine which processing options are made available to the user, and they can be used specifically to support compliance and demonstration of ISO standards within an organization.

Multiple workflows and Watch lists

In this release, multiple workflow files can be added. Each workflow can then be assigned to one or more user groups. The actual workflow displayed on the client depends on which user group the logged-on user belongs to. For more information, contact *ps@msab.com*.

In 6.1, we have added support for import of multiple watch lists to Kiosk, Tablet, and Express clients. You can control which watch lists to apply from the workflow file.




	2		댶		B.		ෂ	C) ()		XE
ms Sið		Logs	Uploads	Reports	Custom reports	Dashboa	rd Settings	Hel	lp About XEC		
									Remove system Recover	Restart	Notify selected Generate reports Edit default K
Systems (3 items,	selected]									DT-DEV73 Actio
Disk s	pace: Th	ere are syste	ms with no di	sk space left.					Only show systems with low HDD r	pace.	Status
Disk s Client Type		ere are syste Unit Id	rrs with no di		0 Status 0	Version 0	HDD space left	. e L	Only show systems with low HDD stores Expiration	pace.	Offine HDD space: 0 GB left (out of 954 GB)
			¢		Status Offline		2	-		pace.	Offine HDD space: 0 GB left (out of 954 GB) (NET.TCP)
Client Type		Unit Id	٥	Site		• 9.0.0	2	0	icense Expiration	pace.	Offine HDD space: 0 GB left (out of 954 GB)

Disk space warning

An administrator often needs to handle many clients at the same time. Now you can get warnings when there is only a certain amount of Disk space left for Kiosks. A red warning shows on top of the client workstations list when there is a Kiosk with low disk space.

ی _{Users}		<u>B</u> oups	늘 ~ Levels	Systems	ф. Sites	E Logs	Uploads	Reports	Custom reports	① Dashboard	Settings	? Help
Classifi	cati	on lev	els									
Classificati	an lev	els										
Level	÷	Name			\$	Description	Users	¢				
0		Diskval				The user hasn't passed the required test or was downgraded due to inactivity						
1	Blaskx					The user has passed the required test but lacks experience						
2		Experiendesas				The user has I	3958					
3		Advanceradest				The user is we	6					
4	Experterna					The user is hi	0					





Microsoft Endpoint **Configuration Manager support**

It is now possible to configure the automatic initial installation of all MSAB products on client workstations via Microsoft Endpoint Configuration Manager. Provide your IT department with the automatic initial installation package to bypass manual configuration. For frictionless installation, enter the XEC Director URL so that clients can automatically contact XFC Director after initial installation.

Microsoft Azure cloud

We have successfully completed the Beta testing of Microsoft Azure cloud integration for automatic uploading of XRY files from the kiosk to the cloud. You can now perform extractions on the kiosk and have them saved automatically in the cloud if required.

For more information, contact *ps@msab.com*.

Secure communication warning

We added a shield icon. You can now directly see whether or not your Kiosk has a secure communication link active via the icon notification.

New settings

In alignment with all the new features listed here, the following settings are updated:

- Enter the limit for low Disk space warnings (default limit: 20 GB)
- Add multiple workflow files and watch lists.
- Set different update and installer paths to update various client platforms (Kiosk, Tablet, Express etc.) smoothly.
- A *net.tcp* file upload service address can now be added.

Improved reporting

Improved analysis in reports with the option to exclude generic Android profiles, SD cards, and SIM card extractions from statistics. By excluding these type of the most common extractions, it allows other more relevant devices to appear in management information report of top device lists.

File upload

File upload permission settings are now available per User group.

Main Technical Support +46 8739 0270

Mon – Thur 8am – 5pm (UTC +1) Friday 8am – 4pm (UTC +1)

Technical Support USA +1 703 750 0162 Mon – Fri 8am – 5pm (UTC – 5)

Email: support@msab.com MSAB Customer Forum: https://forum.msab.com

MSAB

